

## **Hypothesis Testing**

## What is hypothesis testing?

A statistical hypothesis is an assertion or conjecture concerning one or more populations.

To prove that a hypothesis is true, or false, with absolute certainty, we would need absolute knowledge. That is, we would have to examine the entire population.

Instead, hypothesis testing concerns on how to use a random sample to judge if it is evidence that supports or not the hypothesis.

Hypothesis testing is formulated in terms of two hypotheses:

H<sub>0</sub>: the null hypothesis;

H<sub>1</sub>: the alternate hypothesis.

The hypothesis we want to test is if  $H_1$  is \likely" true.

So, there are two possible outcomes:

Reject  $H_0$  and accept  $H_1$  because of su cient evidence in the sample in favor or  $H_1$ ;

Do not reject  $H_0$  because of insu cient evidence to support  $H_1$ .

#### Very important!!

Note that failure to reject  $H_0$  does not mean the null hypothesis is true. There is no formal outcome that says \accept  $H_0$ ." It only means that we do not have su cient evidence to support  $H_1$ .

#### Example

In a jury trial the hypotheses are:

H<sub>0</sub>: defendant is innocent;

H<sub>1</sub>: defendant is guilty.

H<sub>0</sub> (innocent) is rejected if H<sub>1</sub> (guilty) is supported by evidence beyond \reasonable doubt." Failure to reject H<sub>0</sub> (prove guilty) does not imply innocence, only that the evidence is insu cient to reject it.

#### Case study

A company manufacturing RAM chips claims the defective rate of the population is 5%. Let p denote the true defective probability. We want to test if:

 $H_0: p = 0:05$ 

 $H_1: p > 0:05$ 


We are going to use a sample of 100 chips from the production to test.

## Case study (cont.)

Let X denote the number of defective in the sample of 100.

Reject  $H_0$  if X = 10 (chosen \arbitrarily" in this case).

X is called the test statistic.



## Case study (cont.)

Why did we choose a critical value of 10 for this example? Because this is a Bernoulli process, the expected number of defectives in a sample is np. So, if p = 0.05 we should expect 100 0:05 = 5 defectives in a sample of 100 chips. Therefore, 10 defectives would be strong evidence that p > 0.05.

The problem of how to nd a critical value for a desired level of signi cance of the hypothesis test will be studied later.

## Types of errors

Because we are making a decision based on a nite sample, there is a possibility that we will make mistakes. The possible outcomes are:

	H <sub>0</sub> is true	H <sub>1</sub> is true
Do not reject H <sub>0</sub>	Correct decision	Type II error
Reject H <sub>0</sub>	Type I error	Correct decision

#### De nition

The acceptance of  $H_1$  when  $H_0$  is true is called a Type I error. The probability of committing a type I error is called the level of signi cance and is denoted by .

#### Example

Convicting the defendant when he is innocent!

The lower signi cance level, the less likely we are to commit a type I error. Generally, we would like small values of; typically, 0.05 or smaller.

#### Case study continued

So, the level of signi cance is = 0:0282.

#### De nition

Failure to reject  $H_0$  when  $H_1$  is true is called a Type II error. The probability of committing a type II error is denoted by .

Note: It is impossible to compute unless we have a speci c alternate hypothesis.

## Case study continued

```
We cannot compute for H_1: p > 0.05 because the true p
is unknown. However, we can compute it for testing
H_0: p = 0:05 against the alternative hypothesis that
H_1: p = 0:1, for instance.
   = Pr(Type II error) = Pr(reject H<sub>1</sub> when H<sub>1</sub> is true)
      = Pr(X < 10 \text{ when } p = 0:1)
            b(x; n = 100; p = 0:1) = 0:4513
        x=0
```

#### Case study continued

What is the probability of a type II error if p = 0.15?

```
= Pr(Type II error)
= Pr(X < 10 when p = 0:15)
= \sum_{x=0}^{9} b(x; n = 100; p = 0:15) = 0:0551
```

#### E ect of the critical value


Moving the critical value provides a trade-o between and

. A reduction in is always possible by increasing the size of the critical region, but this increases . Likewise, reducing is possible by decreasing the critical region.

## E ect of the critical value (cont.)

#### Case study continued

Lets see what happens when we change the critical value from 10 to 8. That is, we reject H<sub>0</sub> if X 8.



## E ect of the critical value (cont.)

#### Case study continued

The new signi cance level is

= Pr(X 8 when p = 0:05)  
= 
$$\sum_{x=8}^{100} b(x; n = 100; p = 0:05) = 0:128$$
:

As expected, this is a large value than before (it was 0.0282).

# E ect of the critical value (cont.)

#### Case study continued

Testing against the alternate hypothesis  $H_1: p = 0:1$ ,

= 
$$Pr(X < 8 \text{ when p} = 0:1)$$
  
=  $\sum_{x=0}^{3} b(x; n = 100; p = 0:1) = 0:206;$ 

which is lower than before.

Testing against the alternate hypothesis  $H_1: p = 0:15$ ,

= 
$$b(x; n = 100; p = 0:15) = 0:012;$$

again, lower than before.

## E ect of the sample size

Both and can be reduced simultaneously by increasing the sample size.

## Case study continued

Consider that now the sample size is n = 150 and the critical value is 12. Then, reject  $H_0$  if X 12, where X is now the number of defectives in the sample of 150 chips.

## E ect of the sample size (cont.)

#### Case study continued

The signi cance level is

= Pr(X 12 when p = 0:05)  
= 
$$\sum_{x=12}^{150} b(x; n = 150; p = 0:05) = 0:074$$
:

Note that this value is lower than 0.128 for n = 100 and critical value of 8.

## E ect of the sample size (cont.)

#### Case study continued

Testing against the alternate hypothesis  $H_1: p = 0:1$ ,

= 
$$Pr(X < 12 \text{ when p} = 0:1)$$
  
=  $\sum_{x=0}^{x-11} b(x; n = 150; p = 0:1) = 0:171;$ 

which is also lower than before (it was 0.206).

Factorials of very large numbers are problematic to compute accurately, even with Matlab. Thankfully, the binomial distribution can be approximated by the normal distribution (see Section 6.5 of the book for details).

#### **Theorem**

If X is a binomial random variable with n trials and probability of success of each trial p, then the limiting form of the distribution of

Z = p np(1 p) n!1 is the standard normal distribution.

This approximation is good when n is large and p is not extremely close to 0 or 1.

#### Case study continued

Lets recompute with the normal approximation.

= Pr(Type I error) = Pr(X 12 when p = 0:05)  
= 
$$\sum_{x=12}^{150}$$
 b(x; n = 150; p = 0:05)  
=  $\sum_{x=12}^{150}$  p 150 0:05 0:95  
Pr Z  $\sum_{x=12}^{12}$  Pr(Z 1:69)

$$= 1 Pr(Z 1:69) = 1 0:9545 = 0:0455$$
:

Not too bad. . . (It was 0.074.)

#### Case study continued

What if we increase the sample size to n = 500 and the critical value to 40?

The normal approximation should be better since n is larger. p 500 0:05 0:95

$$Pr Z = 40 500 0:05 = Pr(Z 3:08)$$

$$= 1 Pr(Z 3:08) = 1 0:999 = 0:001$$
:

Very unlikely to commit type I error.

#### Case study continued

Testing against the alternate hypothesis  $H_1: p = 0:1$ ,


$$= b(x; n = 500; p = 0:1)$$

$$x=0$$


$$= \frac{100}{100} \frac{100}{100} = \frac{100}{10$$

$$= Pr(Z1:69) = 0:0681:$$


#### Visual interpretation with normal approximation



## Visual interpretation with normal approximation



## Visual interpretation with normal approximation



#### Power of a test

#### De nition

The power of a test is the probability of rejecting  $H_0$  given that a speci c alternate hypothesis is true. That is,

Power = 1:

#### Summary

#### Properties of hypothesis testing

- and are related; decreasing one generally increases the other.
- 2. can be set to a desired value by adjusting the critical value. Typically, is set at 0.05 or 0.01.
- 3. Increasing n decreases both and .
- decreases as the distance between the true value and hypothesized value (H<sub>1</sub>) increases.


#### One-tailed vs. two-tailed tests

In our examples so far we have considered:

 $H_0: =_0$ 

 $H_1: > 0.$ 

This is a one-tailed test with the critical region in the righttail of the test statistic X.




## One-tailed vs. two-tailed tests (cont.)

Another one-tailed test could have the form,

 $H_0: =_0$ 

 $H_1: < 0,$ 

in which the critical region is in the left-tail.




## One-tailed vs. two-tailed tests (cont.)

In a two-tailed test check for di erences:

 $H_0: =_0$ 

 $H_1: 6= 0,$ 




#### Two-tailed test: example

Consider a production line of resistors that are supposed to be 100 Ohms. Assume = 8. So, the hypotheses are:

 $H_0$ : = 100


 $H_1$ : 6= 100,

Let X be the sample mean for a sample of size n = 100.



In this case the test statistic is the sample mean because this is a continuous random variable.

#### Two-tailed test: example (cont.)



We know the sampling distribution of X is a normal p distribution with mean and standard deviation = n = 0:8 due to the central limit theorem.

#### Two-tailed test: example (cont.)

Therefore we can compute the probability of a type I error as

$$= Pr \ Z < 8 = p \ 100 \ ) + Pr(Z > 8 = p \ 100 \ ) + Pr(Z > 8 = p \ 100 \ ) + Pr(Z > 102 \ 100 \ )$$

$$= Pr(Z < 2:5) + Pr(Z > 2:5)$$

$$= 2 Pr(Z < 2:5) = 2 0:0062 = 0:0124$$
:

#### Con dence interval

Testing  $H_0$ : =  $_0$  against  $H_1$ : 6=  $_0$  at a signi cance level is equivalent to computing a 100 (1)% con dence interval for and  $H_0$  if  $_0$  is outside this interval.

#### Example

For the previous example the con dence interval at a signi cance level of 98:76% = 100 (1 0:0124) is [98; 102].

# Tests concerning sample mean

(variance known)

As in the previous example, we are often interested in testing

$$H_0: =_0$$

 $H_1$ : 6= 0,


based on the sample mean X from samples  $X_1$ ;  $X_2$ ; :::;  $X_n$ , with known population variance  $^2$ .

Under  $H_0$ : = 0, the probability of a type I error is computed using the sampling distribution of X, which, due to the central limit theorem, is normal distributed with mean p and standard deviation = n.

(variance known)

From con dence intervals we know that

Pr 
$$z = 2$$
  $x = 2 = 1$ 



(variance known)

Therefore, to design a test at the level of signi cance we choose the critical values a and b as

$$a = \sum_{0} z_{\frac{-2p}{n}}$$

$$b = 0 + z_{\frac{-2p}{n}};$$

then we collect the sample, compute the sample mean X and

reject 
$$H_0$$
 if  $X < a$  or  $X > b$ .

(variance known)

## Steps in hypothesis testing

- 1. State the null and alternate hypothesis
- 2. Choose a signi cance level
- 3. Choose the test statistic and establish the critical region
- Collect the sample and compute the test statistic.
   If the test statistic is in the critical region, reject
   H<sub>0</sub>. Otherwise, do not reject H<sub>0</sub>.

(variance known)

#### Example

A batch of 100 resistors have an average of 102 Ohms. Assuming a population standard deviation of 8 Ohms, test whether the population mean is 100 Ohms at a signi cance level of = 0:05.

#### Step 1:

 $H_0$ : =100

H<sub>1</sub>: 6= 100;

Note: Unless stated otherwise, we use a two-tailed test.

Step 2: = 0.05

(variance known)

#### **Example continued**

Step 3: In this case, the test statistic is speci ed by the problem to be the sample mean X.

Reject  $H_0$  if X < a or X > b, with

$$a = {0 \atop 0} = {2 \atop -2p \atop n} = {0 \atop 0} = {2 \atop 0:025} = {100 \atop 0}$$

$$= 100 \quad 1:96 \frac{8}{10} = 98:432$$

$$b = {0 \atop 0} + {2 \atop 0} = {20 \atop 0} = 100 + 1:96 \frac{8}{10} = 101:568:$$

Step 4: We are told that the test statistic on a sample is X = 102 > b. Therefore, reject  $H_0$ .

# One-sided sample mean test


(variance known)

#### Case A:

In this case, we are interested in testing,

 $H_0: =_0$ 

 $H_1: > 0.$ 



(variance known)

Thus, our decision becomes: reject  $H_0$  at signi cance level if  $X >_0 + z p_n$ :

Note that we use z instead of 
$$z = 2$$
, just as in one-tailed con dence intervals


(variance known)

Case B:

In this case, we are interested in testing,

 $H_0: =_0$ 

 $H_1$ : < 0.



(variance known)

The decision becomes: reject H<sub>0</sub> at signi cance level if

$$X < 0$$
  $p n$ :

(variance known)

#### Example

A quality control engineer nds that a sample of 100 light bulbs had an average life-time of 470 hours. Assuming a population standard deviation of = 25 hours, test whether the population mean is 480 hours vs. the alternative hypothesis < 480 at a signi cance level of = 0:05.

#### Step 1:

 $H_0$ : =480

H<sub>1</sub>: < 480;

Step 2: = 0.05

(variance known)

#### **Example continued**

Step 3: The test statistic is the sample mean X. Reject  $H_0$  if

$$X < 0 \ z \ \overline{p \ n} = 480 \ 1:645 \ \overline{10} = 475:9$$

Step 4: Since X = 470 < 475:9, we reject  $H_0$ .

# Tests concerning sample mean

(variance unknown)

As before, we are often interested in testing

$$H_0: =_0$$

 $H_1$ : 6= 0,

based a sample  $X_1; X_2; :::; X_n$ , but now with unknown

variance. For our decision we use the sample mean X and the sample variance s<sup>2</sup>.

We know that in this case the sampling distribution for X is the t-distribution.

(variance unknown)

usual.

Critical region at signi cance level is, X < a or X > b, where

$$a = \int_{0}^{\infty} t \frac{s}{p \overline{n}}$$

$$b = \int_{0}^{\infty} t = 2 \frac{s}{p \overline{n}};$$

where t = 2 had v = n 1 degrees of freedom.

Equivalently, let  $T = \frac{X_{s=ph}}{s=ph}$ . Reject  $H_0$  if  $T < \frac{t}{s=2}$  or T > t =2, for v = n 1 degrees of freedom. For one-sided tests, t =2 is replaced by t as

(variance unknown)

## Example 10.5 from the textbook

It is claimed that a vacuum cleaner expends 46 kWh per year. A random sample of 12 homes indicates that vacuum cleaners expend an average of 42 kWh per year with (sample) standard deviation 11.9 kWh. At a 0.05 level of signi cance, does this suggest that, on average, vacuum cleaner expend less than 46 kWh per year? Assume the population to be normally distributed.

(variance unknown)

## Example solution:

Step 1:

 $H_0: = 46 \text{ kWh}$ 

 $H_1: < 46 \text{ kWh};$ 

Step 2: = 0.05

(variance unknown)

#### Example solution: continued

Step 3: The test statistic is  $T = \frac{x}{s=pn^{\theta}}$ . Reject H<sub>0</sub> if T < t<sub>0:05</sub> for v = n 1 = 11 degrees of freedom; that is, reject H<sub>0</sub> if T < 1:796.

Step 4: We have that X = 42, s = 11:9 and n = 12. So,  $T = \frac{42 \quad 46}{11 \cdot 9 = 12} = 1:16 > 1:796:$ 

Do not reject H<sub>0</sub>.

## Hypothesis testing using the p-value

In the approach we have taken so far, the signi cance level is pre-selected up front, either by choosing a given value or setting the critical region explicitly. In this case, the nal outcome is the decision.


Now suppose a hypothesis test is performed at a signi cance level of 0.05, but someone else wants to test with a stricter signi cance level of 0.01. This requires recomputing the critical region.

The p-value aims to provide more information about the test statistic with regards to the hypothesis test.

#### De nition

The p-value is the lowest level of signi cance at which the observed value of a test statistic is signi cant (i.e., one rejects H<sub>0</sub>).

Alternative interpretation: the p-value is the minimum probability of a type I error with which H<sub>0</sub> can still be rejected.



#### Example

Suppose that, for a given hypothesis test, the p-value is 0.09. Can  $H_0$  be rejected?

Depends! At a signi cance level of 0.05, we cannot reject  $H_0$  because p = 0.09 > 0.05. However, for signi cance levels greater or equal to 0.09, we can reject  $H_0$ .

#### Example

A batch of 100 resistors have an average of 101.5 Ohms.

Assuming a population standard deviation of 5 Ohms:

- (a) Test whether the population mean is 100 Ohms at a level of signi cance 0.05.
- (b) Compute the p-value.

# Example continued

(a) 
$$H_0$$
: = 100;  $H_1$ : 6= 100

Test statistic is X. Reject H<sub>0</sub> if

or 
$$X<100$$
  $z = 0.025p = 100 = 1.96$   $x = 100 = 1.96$   $x = 100 = 1.96$ 

$$X > 100 + z_{0.025p} = 100 + 1.96$$
  $\overline{}_{10} = 100_{.98}$ 

X = 101:5 therefore, reject  $H_0$ .

#### **Example continued**

(b) The observed z-value is

$$Z = p = p = 5 = 10 = 3$$
:

Then, the p-value is

$$p = 2 Pr(Z > 3) = 2$$
 0:0013 = 0:0026:

This means that  $H_0$  could have been rejected at signicance level = 0:0026 which is much stronger than rejecting it a 0:05.

